

How do I create a PATGuard viewer CD?


PATGuard Viewer is a 'view' only version of the program that can be freely issued to Clients and others so that they can view the database in real-time and also print their own Reports.

Note:

The PATGuard Viewer feature is available with PATGuard Plus, PATGuard Elite and PATGuard Elite SQL only.


This feature enables a customised Viewer CD to be created very easily. A Viewer CD can be created at the database level in which case the entire database will be available to the PATGuard Viewer user or for an individual Client within a database in which case only the data for that Client will be available to the PATGuard Viewer user.

- 1) To create a Viewer CD Image disc, click on the root of the database tree at the upper left side of the Main Window or select an individual Client.




Experts in what we do.

- 2) Right mouse click to display the context menu.



- 3) Select Create Viewer CD Image and the following windows will be displayed:



Create Viewer CD Image dialog box

- 4) To create the Viewer CD image edit the available fields in the Create Viewer CD Image dialog box (or accept defaults).
- 5) Splash Screen
This field is a path to a bitmap file which appears when the PATGuard Viewer is started and replaces the log-in screen.
- 6) Company Logo
This field is a path to a jpeg file which is your company logo and will appear on all PATGuard Viewer Reports.
- 7) CD Image Directory
This field is the path and directory name where the CD image files will be stored.

Important Note:

NEVER make this the root directory or other main directory, e.g. c:\, d:\ etc.

- 8) A message prompt may appear:
Delete image directory contents before creating CD image
Selecting this will ensure that only the newly generated files will be in the directory by deleting all pre-existing files.

Important Note:

Ensure this is not the root directory (or any other important directory)

- 9) Once all the fields are set appropriately, select Create CD Image to generate the CD image files.
- 10) Once created successfully, a message will be displayed to this effect.
- 11) Copy all the files generated and burn onto your new CD using your normal CD creating software programme.

The Viewer CD image consists of a number of files created and stored in the CD image directory. The PATGuard Viewer CD will be created when these files are 'burned' into a new CD.

Note:

Do not copy the directory but copy all the files in the directory to ensure that all the files are directly on the CD and not within a directory. It is a good idea to check the CD is correct by installing on your own PC. DO NOT install PATGuard Viewer onto the same PC as PATGuard Plus Version 5.0 or below.